

Mitered Corner Baby Blanket

For 36" square blanket, cut: One 32" square of flannel for the front of blanket One 42" square of flannel for the back of blanket


Wash and dry your fabric prior to cutting.

Carefully cutting each square of fabric will lead to more perfect results.

Step #1: Prepare Fabric

- -Remove the selvage edge.
- -Cut two pieces of contrasting fabric using the dimensions listed above.

Note: On each piece of fabric, identify and mark the lengthwise grain (same as selvage edges) and the crosswise grain (direction with the most give when lightly stretched).



Step #3: Create Stop Points

- -On the smaller piece of fabric, mark 1/4" from each side at the corner and place a pin for a "stop point." Do so for both corners along the side you are pinning.
- -Sew a $\frac{1}{4}$ " seam from one stop point to the other.
- -Repeat for the opposite side (match centers, pin stop points, and sew).





Step #2: Align and Pin

- -Mark the centers on all four sides of both pieces.
- -Beginning along one edge, place fabric right sides together, matching the center marks. Pin in place.
- -Make sure that the excess material has the same measurement on each end.





Stop Points: sew to it, not through it!

Step #4: Sew Remaining Seams

- -Repeat (match centers, pin stop points, and sew) on the last two sides, leaving a 6" opening in the middle of one side for turning.
- -There will be excess material at each corner once all of the sides have been sewn.

Step #5: Miter Corners

- -Holding the corner, fold the blanket so the two seam edges meet.
- -Mark a line at a 90° angle from the *fold* to the stop point.
- -Stitch along this line. Trim all but 1/4" of the excess.
- -Repeat for each corner.

Tip: You don't even need a ruler for this step. Simply use the corner of a sheet of paper. Align with the **fold**, *not* the raw edge.





90°

raw edge



Step #6: Press and Turn

fold

- -Lay the blanket out flat, small piece on top. Notice that the back panel folds over the front.
- -Press the seams toward the outside edges.
- -Turn the blanket right side out through the gap.
- -Use a pin or point turner to square the corners.

Step #7: Finish

- -Lay the blanket flat so the border is an equal width on all sides.
- -Pin around the blanket at the seams and at the opening where you turned the blanket- being careful to fold the seam allowance under.
- -Press the blanket flat, then top stitch around the blanket by the seam edge (on border side of seam).





Updated handout developed by Margie Memmott and Ariel Peterson. For more detailed instructions visit: http://extension.usu.edu/files/publications/publication/FL_ST_Construction_2007-401pr.pdf. USU fact sheet written by Ronda H. Olsen, Debra Proctor, and Karen Biers.

Utah State University is an affirmative action/equal opportunity institution.